



## **Taurus Version 2.02.05 Release Notes**

### **Release Importance:**

Priority 2 - Important Maintenance Release. Strongly Recommended, Perform As Soon As Practical.

This upgrade will fix anomalous behavior issues associated with software upgrades, swapping of media and data download.

### **Release Relevance:**

This release contains improvements and changes since Taurus Release 2.01.00

### **Software Improvements:**

- eliminated conflicts arising from use of media containing earlier version data STOREs
- improved self-healing capabilities for increased data STORE robustness
- improved software upgrade process and documentation for easier upgrades
- improved data download to eliminate occasional appearance of missing data (data not actually missing, just appeared missing under certain download request conditions)
- eliminated possibility of duplicate data in the downloaded miniSEED files
- eliminates a rare but potential data loss following a re-transmission request from NAQS (only applies if Taurus is streaming data to the Nanometrics Data Acquisition System (NAQS))
- other minor bug fixes

### **New Features:**

- 500 samples per second

### **Known Issues:**

There are no known issues with this release.

### **End of Notes**

---